

TEKLYNX Knowledge Base

How do I connect my LABEL MATRIX network client to the License Server?

Problem

How do I connect a LABEL MATRIX network client to the License Server?

Environment

Microsoft Windows XP Microsoft Windows Vista Microsoft Windows 7 Microsoft Windows Server 2003
Microsoft Windows Sever 2008

Resolution

Launch LABEL MATRIX. An activation prompt should appear. Choose Run as a Trial. Click Finish to close any wizards that appear. Click Tools > Setup and choose the Network tab. Check the Network Key check box. Enter \\ and then the server's name into the Server Location field. Click OK. Restart the program. When the software launches again, it should obtain a license from the server and no longer prompt you to activate.

<http://kb.teklynx.com/knowledgemanager//questions/521/>