

TEKLYNX Knowledge Base

How do I add a network printer?

Problem

How do I add a network printer?

Environment

Microsoft Windows Server 2008 Microsoft Windows 7

Resolution

Open Devices and Printers. Highlight a print driver. Click Print Server Properties at the top of the screen. Go to the Ports Tab. Click the Add Port button. Select the Standard TCP/IP Port option. Click New Port > Next. Enter the IP address in the top line. Click Next > Next > Finish. Open LABELVIEW. Go to File > Select Printer. Click Add. Select the printer from the printers list. Select the port option that shows only the IP address that was entered earlier. Click OK on the next two screens. Print the label.

<http://kb.teklynx.com/knowledgemanager//questions/839/>