

TEKLYNX Knowledge Base

After moving my label files, they cannot connect to the database.

Problem

After moving my label files, they cannot connect to the database.

Environment

Microsoft Windows XP Microsoft Windows Vista Microsoft Windows 7 Microsoft Windows Server 2003
Microsoft Windows Server 2008

Resolution

Open up the label and click on File > Label Properties. Select the Database tab. Click the Reanalyze button. Proceed through the Reanalyze Database Wizard.

Cause

This will often occur when the connection is broken between a label file and the database; if one or the other is moved the connection will break and need to be reanalyzed.

<http://kb.teklynx.com/knowledgemanager//questions/960/>